





Solution to Installation Failure of MM32 USB Driver under WinXP

1. Start the device manager and uninstall the MM32 USB driver that is failed to be installed or enumerated into other devices, as shown in the following figure:







2. Open the system installation path C:\Windows\inf and delete all oem*.inf, oem*.PNF files;



3. Restart the computer, open my computer\properties, and set the driver signature in the hardware options of the system properties;









4. Connect MM32-LINK with PC and open the device manager as shown in the figure; decompress the Driver directory and point to it when installing the driver manually.




amd64	2019/1/10 11:32	文件夹	
x86	2019/1/10 11:32	文件夹	
dpinst_amd64	2010/7/23 21:28	应用程序	1,026 KB
dpinst_x86	2010/7/23 21:28	应用程序	901 KB
install	2018/3/21 11:40	Windows 批处理...	1 KB
mm32cdc	2018/2/11 9:56	安装信息	2 KB
mm32usb	2018/1/26 10:26	安装信息	3 KB
uninstall	2018/3/21 11:40	Windows 批处理...	1 KB
usbser.sys	2013/8/29 8:56	系统文件	26 KB
winusb.sys	2010/11/20 18:43	系统文件	41 KB


5. Follow the following steps to install the MM32-CDC driver;











6. The installation steps of MM32 LINK driver is the same as that of MM32 CDC driver.

